

# ACTAtek Remote Registration Quick Install

21 December, 2016

Version 1.3

ACTAtek (UK) Ltd.

Version 1.3

### DOCUMENT STATUS

<b>Issue</b>	<b>Update</b>	<b>Date</b>	<b>Author</b>	<b>Amendment Summary</b>
		2011/04/12	Shirleen	
		2011/09/15	Peter	Update Figures
		2016/12/21	Peter	Remove Smart Card part

## **Table of Contents**

<i>Table of Contents</i> .....	3
<b>1 Introduction</b> .....	<b>1</b>
1.1 Purpose .....	1
<b>2 Installation</b> .....	<b>1</b>
2.1 Installation Package.....	1
<b>3 Configuring Remote Registration</b> .....	<b>4</b>
<b>4 Registering/Updating fingerprint and smartcard number</b> .....	<b>5</b>

# 1 Introduction


## 1.1 Purpose

This is an internal document to provide the reader an overview of the install and setup required for Remote Registration.

# 2 Installation

## 2.1 Installation Package

The install package comes in 32bit version for both 32bit and 64bit operating systems. Run the **[setup.exe]** to start the installation progress and follow the instructions as stated.






Figure 2: Installer Start-up Screen




Figure 3: Installation folder selection




Figure 3: Confirmation dialog




Figure 4: Installation progress





Figure 5: Installation complete

### 3 Configuring Remote Registration

Run [AMS (DE) Desktop Enrollment] software.

And enter the AMS Server IP address, and also the User Name/Password of AMS Login.

Once done, click [Login] button to get the User lists of AMS.



## 4 Registering/Updating fingerprint

To register or update the user's fingerprint , double-click on the user ID to start to do the enrollment.

The screenshot shows the 'AMS Desktop Enrollment' application window. At the top, there is a menu bar with 'Exit', 'System Config', and 'About'. Below the menu is a 'Search Options' section with input fields for 'UserID', 'First Name', 'Last Name', 'Department', 'Admin Level', and 'Fingerprint', along with a 'Search' button. Below the search section is a pagination area showing '1 / 6' pages, 'Page Size 10', and 'Employees Found: 51'. The main area contains a table with columns for 'ID', 'First Name', 'Last Name', and 'Edit'. The table lists 9 employees, with the first row highlighted in yellow and the second in blue. At the bottom of the window are 'Upload Changes' and 'Discard Changes' buttons.

ID	First Name	Last Name	Edit
1 A999			A999
2 9141			9141
3 1018	Fiazul	Ishan	1018
4 0212162	Rafiqul	Ishan	0212162
5 1001	Masud Asker	Mellick	1001
6 1026	Md. Shajahan	Ishah	1026
7 1008	Md. Anisur	Hossain	1008
8 1021	Sulfi Mohammad Abdul	Rahim	1021
9 1019	Md. Ishah	Munir	1019



1. Select [Enable FingerPrint] ,and [Enable Automatch] option.
2. Select [FLI] as Fingerprint Type.
3. Click [Start Fingerprint Scan] button, and then put the finger 3 times at FingerPrint scanner.
4. Click [Update] button to finish the FingerPrint enrollment.

The screenshot displays the 'User' registration window with the following sections:

- User Details:** Fields for User ID (0213), FirstName (1), and LastName.
- User settings:** Checkboxes for 'Enable FingerPrint' (checked), 'Enable Automatch' (checked), and 'Enable SmartCard' (unchecked).
- SmartCard:** 'Card enrollment' status is 'OFFLINE'. Includes a 'Card Number' field, 'Read' and 'Clear' buttons, and an 'Enable Buzzer' checkbox.
- Fingerprint Enrollment:** 'Fingerprint Type' is set to 'FLI'. 'Scan Quality' is 'HIGH' and 'Number of Templates' is '3'. A central area shows a fingerprint image and a message: 'Enrollment process finished successfully. Quality: 10'. A 'Start Fingerprint Scan' button is highlighted with a red box.
- FingerPrint Image(s):** Three small thumbnail images of fingerprints.
- Buttons:** 'Update' and 'Cancel' buttons are at the bottom, with 'Update' highlighted by a blue box.

- 5.The client can continue to double click the other User ID to do the FingerPrint enrollment.
- 6.Once finished all Users' FingerPrint enrollment,click [Upload Changes] button to update to AMS database.
- 7.After that,AMS will download the Users' FP data to all the registered ACTAtek devices.

